

UEI Hardware

1. Hardware Support.....	1
1.1. UEIDAQ operation	6
2. Analog Input (A/D)	8
2.1. A/D Settings	8
2.1.1. Pacing.....	8
2.1.2. Channel List	8
3. Device Configuration and Hardware Settings	9
3.1. WIN-30 Series	9
3.1.1. Available Modes	9
3.1.2. Base Address	9
3.1.3. DMA Channel	9
3.1.4. Interrupt Level	10
3.1.5. Time Base (A/D Only)	10
3.1.6. Input Ranges (A/D Only)	10
3.1.7. Secondary Buffer (A/D Only).....	10
3.1.8. Output Ranges (D/A Only).....	11
3.1.9. 8255 Setup (Digital In, Digital Out).....	11
3.1.10. Connections	11

1. Hardware Support

		WIN-30D	WIN-30DA
Analog Inputs	Single Ended	16	16
	Differential	-	-
	Simultaneous Sampling	No	No
	Max Sampling Rate	1 MHz	1 MHz
	Resolution	12 bits	12 bits
Digital Inputs	S/W Program Gain	No	No
	Max Sampling Rate	24	24
Counter Timer Inputs		S/W	S/W
Analog Outputs		-	-
		-	4
	Max Output Rate	-	S/W
	Resolution	-	2 16-bit, 2 12-bit
Digital Outputs	S/W Program Gain	-	No
	Max Output Rate	24	24
		S/W	S/W
		WIN-30DS	WIN-30DS/4
Analog Inputs	Single Ended	16	16
	Differential	-	-
	Simultaneous Sampling	Yes	Yes (4 Chs)
	Max Sampling Rate	750,000 Hz	750,000 Hz
	Resolution	12 bits	12 bits
Digital Inputs	S/W Program Gain	No	No
	Max Sampling Rate	24	24
Counter Timer Inputs		S/W	S/W
Analog Outputs		-	-
		4	4
	Max Output Rate	S/W	S/W
	Resolution	2 16-bit, 2 12-bit	2 16-bit, 2 12-bit
Digital Outputs	S/W Program Gain	No	No
	Max Output Rate	24	24
		S/W	S/W
		WIN-30PGH	WIN-30PGL
Analog Inputs	Single Ended	8	8
	Differential	8	8
	Simultaneous Sampling	No	No
	Max Sampling Rate	1 MHz	1 MHz
	Resolution	12 bits	12 bits
Digital Inputs	S/W Program Gain	1,2,4,8	1,10,100,1000
	Max Sampling Rate	24	24
Counter Timer Inputs		S/W	S/W
Analog Outputs		-	-
		4	4
	Max Output Rate	S/W	S/W
	Resolution	2 16-bit, 2 12-bit	2 16-bit, 2 12-bit
Digital Outputs	S/W Program Gain	No	No
	Max Output Rate	24	24
		S/W	S/W

		WIN-30PGSH	WIN-30PGSL
Analog Inputs	Single Ended	8	8
	Differential	8	8
	Simultaneous Sampling	Yes	Yes
	Max Sampling Rate	750,000 Hz	750,000 Hz
	Resolution	12 bits	12 bits
	S/W Program Gain	1,2,4,8	1,10,100,1000
Digital Inputs		24	24
	Max Sampling Rate	S/W	S/W
Counter Timer Inputs		-	-
Analog Outputs		4	4
	Max Output Rate	S/W	S/W
	Resolution	2 16-bit, 2 12-bit	2 16-bit, 2 12-bit
	S/W Program Gain	No	No
Digital Outputs		24	24
	Max Output Rate	S/W	S/W
		WIN-3016D	WIN-3016DA
Analog Inputs	Single Ended	16	16
	Differential	-	-
	Simultaneous Sampling	No	No
	Max Sampling Rate	200,000Hz	200,000Hz
	Resolution	16 bits	16 bits
	S/W Program Gain	No	No
Digital Inputs		24	24
	Max Sampling Rate	S/W	S/W
Counter Timer Inputs		-	-
Analog Outputs		-	4
	Max Output Rate	-	S/W
	Resolution	-	2 16-bit, 2 12-bit
	S/W Program Gain	-	No
Digital Outputs		24	24
	Max Output Rate	S/W	S/W
		WIN-3016DS	WIN-3016DS/4
Analog Inputs	Single Ended	16	16
	Differential	-	-
	Simultaneous Sampling	Yes	Yes (4 chs)
	Max Sampling Rate	200,000 Hz	200,000 Hz
	Resolution	16 bits	16 bits
	S/W Program Gain	No	No
Digital Inputs		24	24
	Max Sampling Rate	S/W	S/W
Counter Timer Inputs		-	-
Analog Outputs		4	4
	Max Output Rate	S/W	S/W
	Resolution	2 16-bit, 2 12-bit	2 16-bit, 2 12-bit
	S/W Program Gain	No	No
Digital Outputs		24	24
	Max Output Rate	S/W	S/W

		WIN-3016PGH	WIN-3016PGL
Analog Inputs	Single Ended	8	8
	Differential	8	8
	Simultaneous Sampling	No	No
	Max Sampling Rate	200,000 Hz	200,000 Hz
	Resolution	16 bits	16 bits
	S/W Program Gain	1,2,4,8	1,10,100,1000
Digital Inputs		24	24
Counter Timer Inputs		S/W	S/W
Analog Outputs		-	-
	Max Output Rate	4	4
	Resolution	S/W	S/W
	S/W Program Gain	2 16-bit, 2 12-bit	2 16-bit, 2 12-bit
Digital Outputs		No	No
		24	24
	Max Output Rate	S/W	S/W
		WIN-3016PGSH	WIN-3016PGSL
Analog Inputs	Single Ended	8	8
	Differential	8	8
	Simultaneous Sampling	Yes	Yes
	Max Sampling Rate	200,000 Hz	200,000 Hz
	Resolution	16 bits	16 bits
	S/W Program Gain	1,2,4,8	1,10,100,1000
Digital Inputs		24	24
Counter Timer Inputs		S/W	S/W
Analog Outputs		-	-
	Max Output Rate	4	4
	Resolution	S/W	S/W
	S/W Program Gain	2 16-bit, 2 12-bit	2 16-bit, 2 12-bit
Digital Outputs		No	No
		24	24
	Max Output Rate	S/W	S/W

The WIN-30 drivers for Snap-Master can accommodate up to eight I/O boards. The maximum number of boards installed in one computer depends on the configuration of the hardware. Each board must have its own unique setting for the Base Address, and Interrupt Level. These settings must also be different from all other components in the computer (such as disk drives, printers, pointing devices, etc.).

This hardware section discusses only special operating instructions unique to the use of UEI hardware with Snap-Master. For detailed specifications and information on the entire range of UEI hardware refer to the WIN-30 Reference Manual supplied with your board.

For information on the settings for each element, please refer to the Data Acquisition section of the Snap-Master User's Manual.

1.1. UEIDAQ operation

There are three components to the UEIDAQ for Snap-Master drivers:

1. The UEIDAQ for Snap-Master driver. This is a DLL which translates Snap-Master function calls to UEIDAQ functions.
2. The UEIDAQ DLL. All I/O requests for any UEI board under Windows 3.1 go via this DLL. It serves to synchronize all driver activity, and allows full multi-tasking.
3. The UEIDAQV virtual device driver. This driver handles all high speed I/O operations, as well as providing access Ring 0 access to the DLL.

Windows support is provided as follows:

1. Windows 3.1 enhanced mode only is supported. Operation under Windows 3.0 or earlier, or in Windows 3.1 standard mode is not possible.
2. A minimum configuration of a 386 processor and 4 MBytes of memory is required. A 386DX or 486 processor and 8 Mbytes of memory are recommended.
3. Windows 3.1 support is via a DLL (Dynamic-Link Library) and a virtual device driver (Vxd). Both of these must be accessible to Windows for the driver system to operate. The DLL is UEIDAQ.DLL, and the Vxd is UEIDAQV.386

4. Windows locates a dynamic-link library by searching the same directories it searches to find an application module. For Windows to find the library, it must be in one of the following directories, which Windows searches in the order listed:
- The current directory.
 - The Windows directory (the directory containing WIN.COM).
 - The Windows system directory (the directory containing such system files as GDI.EXE).
 - Any of the directories listed in the PATH environment variable.
 - Any directory in the list of directories mapped in a network.

Microsoft recommends that DLL's be loaded into the Windows system directory. This is where the default installation program places UEIDAQ.DLL, but any other valid position is acceptable

In order for Windows to load the UEIDAQV Vxd, the following line must appear in the [386ENH] section of the Windows SYSTEM.INI file: "device=c:\uei\ueidaqv.386". This assumes that the Vxd is in the default location, the c:\UEI directory. If it is not, then the line should be modified accordingly. Once again, this is automatically done by the default installation program.

2. Analog Input (A/D)

2.1. A/D Settings

2.1.1. Pacing

WIN-30 boards for Snap-Master operate in burst mode (also called block mode). To use External Pacing, the pacer must provide a pulse for each conversion period. For example, to sample two channels at 1000 Hz each, the pacer must provide a 1000 Hz clock signal, or a pulse every 1/1000th of a second. Consult the WIN-30 Reference Manual for more detailed information on block mode operation and using an external clock.

Several boards in the WIN-30 series support simultaneous sampling (DS, DS/4 and PGS boards). Under Snap-Master, simultaneous sampling is always enabled, and no special action is required to select it.

The WIN-30 series hardware operates with its external trigger permanently enabled. This allows for “gated” pacing using a digital input to the external trigger. When the external trigger input is a logical high, clock pulses are produced for pacing. If the external trigger input goes to a logical low, clock pulses are not produced and the conversions do not occur. Consult the WIN-30 Reference Manual for more detailed information on external trigger operation.


2.1.2. Channel List

All of the WIN-30 series of boards except the PG models support 16 Single-Ended analog input channels. The PG models (WIN-30PGL, WIN-30PGL) support 8 Differential analog input channels. Selecting the correct model from the Configuration dialog automatically sets the correct number of inputs.

3. Device Configuration and Hardware Settings

This section presents the hardware settings for the WIN-30 series of boards, along with the corresponding setting in the Snap-Master Configuration dialog. For more detailed information on specific UEI boards consult the WIN-30 Reference Manual.

3.1. WIN-30 Series



3.1.1. Available Modes

A/D	Software, Hardware
D/A	Software
Digital In	Software
Digital Out	Software

3.1.2. Base Address

The base address is set using switches 3 to 8 on the board's DIP switch. The factory setting is 700 hex (or H700), and takes 32 consecutive address locations (from H700-H71F). For more detailed information on the base address settings consult the WIN-30 Reference Manual.

3.1.3. DMA Channel

Snap-Master does not use DMA with the WIN-30 boards, so no setting is required and this control is disabled.


3.1.4. Interrupt Level

The WIN-30 series of boards have a software programmable Interrupt Level. The IRQ can be set to 2, 3, 5, 7, 10, 11, 12, 14, or 15. Each board **MUST** have a unique IRQ Level. Refer to Appendix E for information on the standard allocations for interrupts in a PC.

3.1.5. Time Base (A/D Only)


The WIN-30 drivers for Snap-Master make use of a 10 Mhz timer clock as shown in the Time Base dialog. This setting is made automatically so no further input is required.

3.1.6. Input Ranges (A/D Only)



The global range for all A/D inputs is software settable using the Input Ranges dialog from the Configuration. For the PG models, the channel gains are set from the A/D Settings dialog.

3.1.7. Secondary Buffer (A/D Only)



The secondary buffer allows large data sets to be acquired. This is especially important with the high acquisition rates of the WIN-30 series boards. The WIN-30 hardware driver sends data from the hardware to the buffer specified in the Secondary Buffer dialog first, then from the secondary buffer to Snap-Master.


The default setting of 2048 KB (or 2 MB) works well for most data acquisition tasks. If you receive a "Buffer Memory Overflow" error message in the Status Log, the size of the Secondary Buffer should be increased.

3.1.8. Output Ranges (D/A Only)

The range of the D/A board outputs is Bipolar ($\pm 5V$) when set to the WIN-30 mode. It is not necessary to select an output range for the hardware.

In Snap-Master, channels 0 and 1 are the 16-bit output channels and channels 2 and 3 are the 12-bit output channels.

3.1.9. 8255 Setup (Digital In, Digital Out)



The 8255 Setup dialog specifies which digital ports are used as inputs (Digital In) and which are used for outputs (Digital Out). The 8255 Selection selects the 8255 chip being programmed (for hardware with a single 8255 chip, this is always 1). The corresponding digital bit numbers will be posted near each of the programmable port names (A, B, C Upper, or C Lower).

3.1.10. Connections

The WIN-30 series boards have two 50-pin connectors - one for analog signals (on the back plate of the board) and one for digital signals (on the board at a right angle to the back plate). The following diagrams show the signal locations on the connectors in case you want to provide your own termination.

<u>Single-Ended</u>	<u>Differential</u>	<u>Pin</u>		<u>Differential</u>	<u>Single-Ended</u>
A/D 0	A/D 0 High	1	2	A/D 0 Low	A/D 8
Analog Ground		3	4	A/D 1 Low	A/D 9
A/D 1	A/D 1 High	5	6	Analog Ground	
A/D 2	A/D 2 High	7	8	A/D 2 Low	A/D 10
Analog Ground		9	10	A/D 3 Low	A/D 11
A/D 3	A/D 3 High	11	12	Analog Ground	
A/D 4	A/D 4 High	13	14	A/D 4 Low	A/D 12
Analog Ground		15	16	A/D 5 Low	A/D 13
A/D 5	A/D 5 High	17	18	Analog Ground	
A/D 6	A/D 6 High	19	20	A/D 6 Low	A/D 14
Analog Ground		21	22	A/D 7 Low	A/D 15
A/D 7	A/D 7 High	23	24	Analog Ground	
(no connection)		25	26	D/A 0 (16 bit)	
Analog Ground		27	28	D/A 1 (16 bit)	
D/A 2 (12 bit)		29	30	D/A 3 (12 bit)	
Ground		31	32	-12 Volts	
+12 Volts		33	34	External Trigger	
External Clock		35	36	Digital Ground	
STB+		37	38	STB-	
Digital Ground		39	40	Digital I/O Port B0	
Digital I/O Port B1		41	42	Digital Ground	
Digital I/O Port B2		43	44	Digital I/O Port B3	
Digital Ground		45	46	Digital I/O Port B4	
Digital I/O Port B5		47	48	Digital I/O Port B6	
Digital I/O Port B7		49	50	Digital Ground	

WIN-30 Analog Connections

	<u>Pin</u>		
Digital I/O Port A0	1	2	Digital Ground
Digital I/O Port A1	3	4	Digital Ground
Digital I/O Port A2	5	6	Digital Ground
Digital I/O Port A3	7	8	Digital Ground
Digital I/O Port A4	9	10	Digital Ground
Digital I/O Port A5	11	12	Digital Ground
Digital I/O Port A6	13	14	Digital Ground
Digital I/O Port A7	15	16	Digital Ground
Digital I/O Port B0	17	18	Digital Ground
Digital I/O Port B1	19	20	Digital Ground
Digital I/O Port B2	21	22	Digital Ground
Digital I/O Port B3	23	24	Digital Ground
Digital I/O Port B4	25	26	Digital Ground
Digital I/O Port B5	27	28	Digital Ground
Digital I/O Port B6	29	30	Digital Ground
Digital I/O Port B7	31	32	Digital Ground
Digital I/O Port C0	33	34	Digital Ground
Digital I/O Port C1	35	36	Digital Ground
Digital I/O Port C2	37	38	Digital Ground
Digital I/O Port C3	39	40	Digital Ground
Digital I/O Port C4	41	42	Digital Ground
Digital I/O Port C5	43	44	Digital Ground
Digital I/O Port C6	45	46	Digital Ground
Digital I/O Port C7	47	48	Digital Ground
+5 Volts	49	50	Digital Ground

WIN-30 Digital Connections